

Parts: Create, Edit and Clone

Sytewise Parts are attached to [Fixtures](#). A parts list is associated with fixtures. To create a new part:

1. Go to the Fixture that will have the part being created.
2. In the right column below the Fixture details and click "New Part"
3. Fill out the form and click "Save".

Parts have the following attributes.

- **A Part Number:** (Required, 60 characters) You can use a serial number or something descriptive. Both the Part Number and Description appear on the part list on the fixture page so descriptions can be confined to the description field
- **Description:** (Required) Here is where you give useful descriptive text like Fan Belt.
- **Installed Date:** (Required) Default: day the part was entered. You can change this to an earlier date if the part was installed at a different time.
- **Position:** (Optional, 12 characters) A short description of the location of the part on the fixture: "Front", "Left", "Top" or simply "A" works. This field sorts the parts list after Part Number and Description.
- **Model Number:** (Optional, 80 characters)
- **Warranty Expiration Date:** (Optional) If a warranty is applicable, enter the expiration date.
- **Warranty Description:** (Optional) Who services the warranty or other terms.
- **Table Details:** (Optional) use this field to create a table of additional data if needed. Each table row per line. Column breaks with commas.



[\[Front\]](#) HVAC SN 4518P29363 2018 20 Ton 410A GAS Package Unit



MFG: Carrier **MDL#:** 48HCFD24B2M6A0A4jp

[\[wo\]](#) Mon Mar 29, 2021 12:01:19 AM

Parts are either Status “On” or “Off”



Image not found. The unknown

Admins can change the status of any part simply by clicking the green or red toggle. Once you've changed the all the part statuses make sure to click "Save" at the top of the list.

[Surveys](#) and [Work Orders](#) can affect changes to parts statuses as well.

Cloning Parts

You can clone any part already created in your account. This may come in handy if you have redundant parts, especially ones with a lot of detail. Cloning parts places the cloned part within the original Fixture. To copy a part (or a select set of parts) into another fixture look into create a Library of that part (or parts) to reuse elsewhere.

To Clone a Part:

1. Navigate to the fixture where the part is going to be cloned.
2. In the listing of parts check the checkbox on the right side next to the print icon.
 1. You can only check one part to clone.
 2. To copy more than one part use the Library feature
3. Click "Clone" at the top of the Parts list.
4. Enter a position if necessary for this copy of the part.
5. Change the part number to help identify this part from the original. Alternately, position can serve as the differentiator.

Clone This Part

×

Position

Back

Part No

HVAC SN 4518P29363

Close

Save

Revision #4

Created Wed, May 25, 2022 6:57 PM by [Joe Smith](#)

Updated Wed, May 25, 2022 7:29 PM by [Joe Smith](#)